

A horizontal barcode consisting of vertical bars of varying heights and widths, spanning the width of the page above the title.

Logic|6


audio

Music Production Software

> Version 6.0, January 2003

> English

Reference-Addendum

A horizontal barcode consisting of vertical bars of varying heights and widths, spanning the width of the page at the bottom.

Emagic Soft- und Hardware GmbH— Software License Agreement

PLEASE READ THIS SOFTWARE LICENSE AGREEMENT (“LICENSE”) BEFORE USING THE SOFTWARE. BY USING THE SOFTWARE, YOU ARE AGREEING TO BE BOUND BY THE TERMS OF THIS LICENSE. IF YOU ARE ACCESSING THE SOFTWARE ELECTRONICALLY, SIGNIFY YOUR AGREEMENT TO BE BOUND BY THE TERMS OF THIS LICENSE BY CLICKING THE “AGREE/ACCEPT” BUTTON. IF YOU DO NOT AGREE TO THE TERMS OF THIS LICENSE, RETURN THE EMAGIC SOFTWARE TO THE PLACE WHERE YOU OBTAINED IT FOR A REFUND OR, IF THE SOFTWARE WAS ACCESSED ELECTRONICALLY, CLICK “DISAGREE/DECLINE”.

IMPORTANT NOTE: To the extent this software may be used to reproduce materials, it is licensed to you only for reproduction of materials you are authorized or legally permitted to reproduce.

1. General. The software, documentation and any fonts accompanying this License whether on disk, in read only memory, on any other media or in any other form (collectively the “EMAGIC Software”) are licensed, not sold, to you by Emagic Soft-und Hardware GmbH (“EMAGIC”) for use only under the terms of this License, and EMAGIC reserves all rights not expressly granted to you. The rights granted herein are limited to EMAGIC’s and its licensors’ intellectual property rights in the EMAGIC Software and do not include any other patents or intellectual property rights. You own the media on which the EMAGIC Software is recorded but EMAGIC and/or EMAGIC’s licensor(s) retain ownership of the EMAGIC Software itself. The terms of this License will govern any software upgrades provided by EMAGIC that replace and/or supplement the original EMAGIC Software product, unless such upgrade is accompanied by a separate license in which case the terms of that license will govern.

2. Permitted License Uses and Restrictions. This License allows you to simultaneously install the EMAGIC Software on any number of computers which you or your organization owns or leases, however, only one copy of the EMAGIC Software may be in use at any given time. The EMAGIC Software may be used to reproduce materials so long as such use is limited to reproduction of non-copyrighted materials, materials in which you own the copyright, or materials you are authorized or legally permitted to reproduce. You may make backup copies of the EMAGIC Software as reasonably necessary in machine-readable form; provided that each backup copy includes all copyright or other proprietary notices contained on the original. Except as and only to the extent expressly permitted in this License or by applicable law, you may not copy, decompile, reverse engineer, disassemble, modify, or create derivative works of the EMAGIC Software or any part thereof. THE EMAGIC SOFTWARE IS NOT INTENDED FOR USE IN THE OPERATION OF NUCLEAR FACILITIES, AIRCRAFT NAVIGATION OR COMMUNICATION SYSTEMS, AIR TRAFFIC CONTROL SYSTEMS, LIFE SUPPORT MACHINES OR OTHER EQUIPMENT IN WHICH THE FAILURE OF THE EMAGIC SOFTWARE COULD LEAD TO DEATH, PERSONAL INJURY, OR SEVERE PHYSICAL OR ENVIRONMENTAL DAMAGE.

3. Transfer. You may not rent, lease, lend or sublicense the EMAGIC Software. You may, however, make a one-time permanent transfer of all of your license rights to the EMAGIC Software to another party, provided that: (a) the transfer must include all of the EMAGIC Software, including all its component parts, original media, printed materials and this License; (b) you do not retain any copies of the EMAGIC Software, full or partial, including copies stored on a computer or other storage device; and (c) the party receiving the EMAGIC Software reads and agrees to accept the terms and conditions of this License.

NFR (Not for Resale) Copies: Notwithstanding other sections of this License, EMAGIC Software labeled or otherwise provided to you on a promotional basis may only be used for demonstration, testing and evaluation purposes and may not be resold or transferred.

4. Termination. This License is effective until terminated. Your rights under this License will terminate automatically without notice from EMAGIC if you fail to comply with any term(s) of this License. Upon the termination of this License, you shall cease all use of the EMAGIC Software and destroy all copies, full or partial, of the EMAGIC Software.

5. Limited Warranty on Media. EMAGIC warrants the media on which the EMAGIC Software is recorded and delivered by EMAGIC to be free from defects in materials and workmanship under normal use for a period of ninety (90) days from the date of original retail purchase. Your exclusive remedy under this Section shall be, at EMAGIC's option, a refund of the purchase price of the product containing the EMAGIC Software or replacement of the EMAGIC Software which is returned to EMAGIC or an EMAGIC authorized representative with a copy of the receipt. THIS LIMITED WARRANTY AND ANY IMPLIED WARRANTIES ON THE MEDIA INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, OF SATISFACTORY QUALITY, AND OF FITNESS FOR A PARTICULAR PURPOSE, ARE LIMITED IN DURATION TO NINETY (90) DAYS FROM THE DATE OF ORIGINAL RETAIL PURCHASE. SOME JURISDICTIONS DO NOT ALLOW LIMITATIONS ON HOW LONG AN IMPLIED WARRANTY LASTS, SO THE ABOVE LIMITATION MAY NOT APPLY TO YOU. THE LIMITED WARRANTY SET FORTH HEREIN IS THE ONLY WARRANTY MADE TO YOU AND IS PROVIDED IN LIEU OF ANY OTHER WARRANTIES (IF ANY) CREATED BY ANY DOCUMENTATION OR PACKAGING. THIS LIMITED WARRANTY GIVES YOU SPECIFIC LEGAL RIGHTS, AND YOU MAY ALSO HAVE OTHER RIGHTS WHICH VARY BY JURISDICTION.

6. Disclaimer of Warranties. YOU EXPRESSLY ACKNOWLEDGE AND AGREE THAT USE OF THE EMAGIC SOFTWARE IS AT YOUR SOLE RISK AND THAT THE ENTIRE RISK AS TO SATISFACTORY QUALITY, PERFORMANCE, ACCURACY AND EFFORT IS WITH YOU. EXCEPT FOR THE LIMITED WARRANTY ON MEDIA SET FORTH ABOVE AND TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, THE EMAGIC SOFTWARE IS PROVIDED "AS IS", WITH ALL FAULTS AND WITHOUT WARRANTY OF ANY KIND, AND EMAGIC AND EMAGIC'S LICENSORS (COLLECTIVELY REFERRED TO AS "EMAGIC" FOR THE PURPOSES OF SECTIONS 6 AND 7) HEREBY DISCLAIM ALL WARRANTIES AND CONDITIONS WITH RESPECT TO THE EMAGIC SOFTWARE, EITHER EXPRESS, IMPLIED OR STATUTORY, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES AND/OR CONDITIONS OF MERCHANTABILITY, OF SATISFACTORY QUALITY, OF FITNESS FOR A PARTICULAR PURPOSE, OF ACCURACY, OF QUIET ENJOYMENT, AND NON-INFRINGEMENT OF THIRD PARTY RIGHTS. EMAGIC DOES NOT WARRANT AGAINST INTERFERENCE WITH YOUR ENJOYMENT OF THE EMAGIC SOFTWARE, THAT THE FUNCTIONS CONTAINED IN THE EMAGIC SOFTWARE WILL MEET YOUR REQUIREMENTS, THAT THE OPERATION OF THE EMAGIC SOFTWARE WILL BE UNINTERRUPTED OR ERROR-FREE, OR THAT DEFECTS IN THE EMAGIC SOFTWARE WILL BE CORRECTED. NO ORAL

OR WRITTEN INFORMATION OR ADVICE GIVEN BY EMAGIC OR AN EMAGIC AUTHORIZED REPRESENTATIVE SHALL CREATE A WARRANTY. SHOULD THE EMAGIC SOFTWARE PROVE DEFECTIVE, YOU ASSUME THE ENTIRE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION. SOME JURISDICTIONS DO NOT ALLOW THE EXCLUSION OF IMPLIED WARRANTIES OR LIMITATIONS ON APPLICABLE STATUTORY RIGHTS OF A CONSUMER, SO THE ABOVE EXCLUSION AND LIMITATIONS MAY NOT APPLY TO YOU.

7. Limitation of Liability. TO THE EXTENT NOT PROHIBITED BY LAW, IN NO EVENT SHALL EMAGIC BE LIABLE FOR PERSONAL INJURY, OR ANY INCIDENTAL, SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES WHATSOEVER, INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, LOSS OF DATA, BUSINESS INTERRUPTION OR ANY OTHER COMMERCIAL DAMAGES OR LOSSES, ARISING OUT OF OR RELATED TO YOUR USE OR INABILITY TO USE THE EMAGIC SOFTWARE, HOWEVER CAUSED, REGARDLESS OF THE THEORY OF LIABILITY (CONTRACT, TORT OR OTHERWISE) AND EVEN IF EMAGIC HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. SOME JURISDICTIONS DO NOT ALLOW THE LIMITATION OF LIABILITY FOR PERSONAL INJURY, OR OF INCIDENTAL OR CONSEQUENTIAL DAMAGES, SO THIS LIMITATION MAY NOT APPLY TO YOU. In no event shall EMAGIC's total liability to you for all damages (other than as may be required by applicable law in cases involving personal injury) exceed the amount of fifty dollars (\$50.00). The foregoing limitations will apply even if the above stated remedy fails of its essential purpose.

8. Export Law Assurances. You may not use or otherwise export or reexport the EMAGIC Software except as authorized by United States law and the laws of the jurisdiction in which the EMAGIC Software was obtained. In particular, but without limitation, the EMAGIC Software may not be exported or re-exported (a) into (or to a national or resident of) any U.S. embargoed countries (currently Cuba, Iran, Iraq, Libya, North Korea, Sudan and Syria), or (b) to anyone on the U.S. Treasury Department's list of Specially Designated Nationals or the U.S. Department of Commerce Denied Person's List or Entity List. By using the EMAGIC Software, you represent and warrant that you are not located in, under control of, or a national or resident of any such country or on any such list.

9. Government End Users. The EMAGIC Software and related documentation are "Commercial Items", as that term is defined at 48 C.F.R. §2.101, consisting of "Commercial Computer Software" and "Commercial Computer Software Documentation", as such terms are used in 48 C.F.R. §12.212 or 48 C.F.R. §227.7202, as applicable. Consistent with 48 C.F.R. §12.212 or 48 C.F.R. §227.7202-1 through 227.7202-4, as applicable, the Commercial Computer Software and Commercial Computer Software Documentation are being licensed to U.S. Government end users (a) only as Commercial Items and (b) with only those rights as are granted to all other end users pursuant to the terms and conditions herein. Unpublished-rights reserved under the copyright laws of the United States.

10. Controlling Law and Severability. This License will be governed by the laws of the Federal Republic of Germany.

11. Complete Agreement; Governing Language. This License constitutes the entire agreement between the parties with respect to the use of the EMAGIC Software licensed hereunder and supersedes all prior or contemporaneous understandings regarding such subject matter. No amendment to or modification of this License will be binding unless in writing and signed by EMAGIC. Any translation of this License is done for local requirements and in the event of a dispute between the English and any non-English versions, the English version of this License shall govern.

12. MPEG-2 Notice. To the extent that the EMAGIC Software contains MPEG-2 functionality, the following provision applies: ANY USE OF THIS PRODUCT OTHER THAN CONSUMER PERSONAL USE IN ANY MANNER THAT COMPLIES WITH THE MPEG-2 STANDARD FOR ENCODING VIDEO INFORMATION FOR PACKAGED MEDIA IS EXPRESSLY PROHIBITED WITHOUT A LICENSE UNDER APPLICABLE PATENTS IN THE MPEG-2 PATENT PORTFOLIO, WHICH LICENSE IS AVAILABLE FROM MPEG LA, L.L.C., 250 STEELE STREET, SUITE 300, DENVER, COLORADO 80206.

1 General 9

- 1.1 New Way to Set the Dialog Language 9

2 Mixer 10

- 2.1 Channel EQ 10
 - 2.1.1 Inserting a Channel EQ 12
 - 2.1.2 Setting EQ Parameters 12
- 2.2 Tape Delay 16
- 2.3 Groups 17
 - 2.3.1 Assigning a Channel to a Group 17
 - 2.3.2 Group Settings 18
 - 2.3.3 Group Automation 19
 - 2.3.4 Group Handling on the Logic Control 19
 - 2.3.5 Supported Control Surfaces 20
- 2.4 Automation Quick Access 20
 - 2.4.1 Setting Up Automation Quick Access 20
- 2.5 New Options for Digital Mixdown/Bounce 21
 - 2.5.1 Bouncing MP3 Format Audio Files 21
 - 2.5.2 Bounce Mode 23

3 Arrange Window 25

- 3.1 Freeze 25
 - 3.1.1 Concept 25
 - 3.1.2 Application 26
 - 3.1.3 How to Freeze a Track 27
 - 3.1.4 Freeze Files 29
- 3.2 Arrange Channel Strip 30
- 3.3 Sample-accurate Waveform Display 31
- 3.4 New Arrange Icons 31
 - 3.4.1 User-definable Icons 31
 - 3.4.2 Icon Color 32

4 Editor Windows 33

- 4.1 Chord Recognition in the Matrix Editor 33

5 Audio Standard Support 34

5.1 MP3 Support (Mac OS X only) 34

5.1.1 MP3 Import 34

5.1.2 MP3 Export 34

6 Project Manager 37

1 General

1.1 New Way to Set the Dialog Language

The Mac OS X version of Logic 6 features a new, Mac OS X compliant, way to set the dialog language (the “Display” Preference that was previously used has been removed):

- Select the Logic 6 application in the Finder.
- Press **⌘I** (to open the Information dialog).
- Select/Flip open the “Languages” section.
- Choose the preferred language, and uncheck all other languages.

2 Mixer

2.1 Channel EQ

The Channel EQ of Logic 6 replaces the track EQ which you know from older versions of Logic. The new equalizer offers a couple of advantages:

- improved, extremely high sound quality
-
- expanded range for gain and Q, and a higher frequency resolution (even when compared with the Fat EQ)
- needs less space on the surface of mixer channels
- better clarity (via thumbnails) for EQ curves
- variable position in the signal flow (i. e. can also be placed between plug-ins)
- integrated FFT analyzer (pre/post EQ)
- large graphic display with complete, and intuitive, parameter editing

The integrated precision analyzer (based on Fast Fourier Transformation algorithms—FFT) shows the energy (amplitude) of all frequency components of the signal. The central display of the Channel EQ fulfills multiple display functions: it shows both the curve of the FFT analyzer and the EQ curve. An identically scaled frequency axis is shown for both. This allows you to easily recognize unwanted frequencies in the analyzer curve, while using the EQ to edit them accordingly.

You can switch the analyzer pre or post EQ in order to compare the original signal with your edits. You can, of course, also judge the excellent quality of the Channel EQ with your ears. We are sure you will be as excited with the results as we are!




Using the Channel EQ as the Default

In order to be backwards-compatible with songs created in Logic version 5 or earlier, the old track EQ is still available. All songs that don't make use of the old track EQ are automatically switched to use the new Channel EQ.


If your existing Autoload song uses pre-set track EQs, you should modify it: Remove the track EQs from all channels. Open Options > Song Settings and switch to the Old Songs page. Deactivate the *Use pre-Logic 6 track EQ* checkbox and resave your Autoload song (i. e. replace it). You can now use the Channel EQ in all new songs created with Logic 6.

- ⓘ Please note that the track EQs of older songs are lost by activating this option. If you don't want this to occur, you can use the Channel EQ of Logic 6 as a plug-in in older songs. Doing so will, however, be at the expense of the Thumbnail view and editing via the EQ page of the Logic Control.

 Please note that the Channel EQ has four bands in the Audio version of Logic and eight bands in the Gold and Platinum versions. If songs with an 8-band EQ from those versions are opened in the Audio version, the settings for the additional bands are ignored, but preserved. Hence, after being edited in the Audio version, the songs can be reopened in the Gold and Platinum versions without any loss of information.

2.1.1 Inserting a Channel EQ

The Channel EQ is inserted into the first available insert slot by double-clicking the *EQ* area on the upper portion of mixer channel strips. This area will change to a thumbnail view of the Channel EQ display. The thumbnails provide an overview of the EQ settings used in each individual channel.

-double-clicking will insert the EQ as the first plug-in and move all existing plug-ins of this channel one slot down (and redirecting their automation data accordingly, if necessary).

Alternatively, you can insert the Channel EQ in any desired slot as per other plug-ins. You'll find it in the EQ section of the plug-in list. This is the only way to insert multiple Channel EQs. (Remember that only the first Channel EQ can be displayed as a thumbnail).


2.1.2 Setting EQ Parameters

The *Band Type* buttons above the display switch individual bands on or off.

You can set/adjust the band parameters either directly in the central EQ display, or in the parameter area below it. As you move the mouse horizontally over the display, pivot marks for individual bands appear on the frequency axis, while the parameter area of the same band is highlighted. The following possibilities are available for changing the parameters of a band:

- Move the mouse horizontally over the display until the desired band is highlighted. Now click-hold the mouse button on the display background (not directly on a pivot point): vertical mouse movements change the *Gain*, horizontal movements change the *Frequency* of this band.
- Click-hold directly on the (illuminated) pivot point of the desired band: vertical movements (up/down) change the *Q* value. The direction required to increase or decrease the *Q* value depends on whether you are above or below the zero line (this ensures that “up” increases, and “down” decreases the volume in this band—you will find this intuitively “correct”). Again, horizontal movements (left/right) change the *Frequency* of the band.
- Click-hold on the desired parameter in the parameter area below the graphic display (*Frequency, Gain or Q*): Moving up increases, and down decreases, the value.






As long as your mouse arrow is in the access area of a band, its individual curve will be graphically inserted over the resulting curve of the entire equalizer.

-  You can also edit Channel EQs via the Logic Control—by pushing the EQ button: this will open the first Channel EQ of the selected channel. If no Channel EQ is active/available, it will automatically be inserted in the first free insert slot.

Parameter Description

The maximum *Gain* per channel is $\pm 24\text{dB}$, the *Frequency* ranges from 20Hz to 20.000Hz . The range of *Q* values depends on the band. The individual bands are defined as follows:

-
- Bands 1 and 4 are shelving equalizers. Their values for *Q* (steepness of their curves) range from 0.10 to 2.00 .
- Bands 2 and 3 are so called “bell” or “peaking” equalizers. *Q* can range from 0.10 to 100 . When set to 100 , the equalizers only apply to a very narrow band, and can work in a similar fashion to notch filters.


-  If *Show EQs* is activated in the parameter box of a channel, it is possible to see a thumbnail view of the Channel EQ displayed in the upper corner of a channel strip.
-  You can reset all settings of the highlighted EQ band (except frequency) by -clicking in the display area.
-  You can reset individual parameters by -clicking in the parameter area.

Master Gain

This fader adjusts the output level of a Channel EQ. This allows you to compensate for level changes introduced by your EQ settings. *Master Gain* has a range of ± 24 dB.


Analyzer On/Off

This button allows you to activate/deactivate the FFT analyzer.

-  Please note that the FFT analyzer needs additional CPU resources. In fact, resource consumption increases significantly at higher resolutions (see below)! We recommend that you disable the analyzer or close the Channel EQ window after setting the desired EQ parameters. This will free up CPU resources for other tasks.

Analyzer Mode

This flip menu determines the location of the analyzer, either in the Input (pre EQ) or Output (post EQ) of the equalizer section.


-  The *Analyzer pre EQ* and *Analyzer post EQ* options allow you to visually compare the original and EQ'ed signals.

Analyzer Resolution

This flip menu defines the resolution of the FFT analyzer—or more accurately, the number of frequency bands. This determines not only the precision of measurements, but also the amount of CPU power needed. The options are as follows:

- *Resolution low (1024 points)*
- *Resolution medium (2048 points)*

- *Resolution high (4096 points)*

 Higher resolutions are necessary whenever you need reliable results in the area of very low bass frequencies. (The bands derived from FFT analysis are divided in accordance with the frequency linear principle—non-technically, this means that there are far more bands in the highest octave than in the lowest).

dB Warp and Analyzer Top

These two parameters allow you to change the vertical scale of the EQ and analyzer curves.

dB Warp allows you to increase the resolution of the EQ *Gain* parameter in the most interesting area around the zero line. Click-holding in the green *dB* scale on the left side of the graphic display, and moving the mouse up will increase it (down to decrease). The overall range is always $\pm 30\text{dB}$, but small values will be easier to recognize.

As soon as the Analyzer is activated, you can change the *Analyzer Top* parameter, which alters the scaling of the FFT analyzer, on the right side of the graphic display. The visible area represents a dynamic range of 60 dB, but by click-holding and vertically dragging, you can adjust the maximum value between $+20\text{ dB}$ and -40 dB . The Analyzer display is always dB-linear.

2.2 Tape Delay

The additional parameters of the Tape Delay [previously reached via 001011 button] have been integrated into its graphical user interface. As a result, the functionality of these parameters have changed slightly, as indicated in the following text.



There is a new *Sync* button. When the *Sync* button is engaged, the delay is synchronized to the song tempo of Logic 6. In this mode, the plug-in uses the internal tempo of Logic Platinum to determine the delay time. The sole purpose of the *Tempo* box is to display the current *bpm* value. This is as per the use of the Tape Delay in the past.

Disengage *Sync* if you would like to adjust the delay time independently of the song tempo (or change the song tempo without changing the delay time). In this mode, the *bpm* value or *ms* values can be altered freely by click-holding in the *Tempo* or *Delay* (time) parameter fields while dragging up or down with the mouse. Note that click-dragging on the left-hand side of *Delay* field will increment the *ms* values in large steps. Click-dragging on the right-hand portion of the field will increment the *ms* values in small steps. Delay time is adjustable between 0 and 1260 *ms*.

The *Freeze* parameter captures the current delay repeats, and sustains them until the *Freeze* parameter is released.

The Tape Delay includes an LFO for delay time modulation. Use it to produce chorus-like effects—even with long delays. The LFO offers adjustable *Speed* and *Depth* controls.

Flutter simulates the tape speed irregularities of the tape transports found in analog tape delay machines, and is adjustable in *Rate* and *Intensity*.

Smooth determines how quickly the “analog tape” can change its speed when switching between different note values. It also evens out the effect of LFO modulation and tape flutter. Pitch changes caused by the use of LFO modulation or *Flutter* will sound less pronounced when the *Smooth* value is increased.

2.3 Groups

Logic 6 introduces Groups. A Group allows you to combine multiple channel strips in order to link their volume faders and mute buttons. If, for example, multiple audio tracks (with individual choir voices) are assigned to one Group, changing the volume of one choir track changes the volumes of all choir tracks. Individual level relationships—at the time the channels assigned to the Group—are retained.


Groups can also link the selection of objects in the Arrange window, thereby linking all edit operations you perform on grouped tracks.

Up to 32 Groups can be created. Each channel can be a member of multiple Groups.


2.3.1 Assigning a Channel to a Group

There is a new Group display in the channel—above the automation mode display. Clicking on the Group display opens the Group flip menu where one of the 32 Groups can be chosen, turned “off”, or the “Group Settings ...” dialog window launched.

Overlapping Groups

One channel can belong to more than one group. To assign an additional group to a channel, press  while choosing a Group via the Group flip menu.

Fast Assignment

Groups can be quickly set and cleared by holding  when clicking on the Group display. The last Group setting—also overlapping groups—will be applied to the current channel, without opening the flip menu.

2.3.2 Group Settings

The Group flip menu (of the Group display) also allows you to open the “Group Settings ...”. In the group setting dialog, the following options can be set for each individual group:

Name

You can name each group.

Enable

A group can be completely disabled here.

Arrange Selection (Edit)

Selecting an arrange object on one member track of a group selects the same horizontal range of all member tracks.

Arrange Track Zoom

Zooming an individual track of a group will zoom all members.

Arrange Track Hide

Hiding an individual track of a group will hide all members.

Arrange Track Record

Record enable/disable of an individual track of a group will record enable/disable all members.

Automation Mode

Changing the automation mode of an individual track of a group will change the automation mode for all members.

Instrument Color

Changing the color of one group member channel will assign this color to all group member channels.

Volume

Changing the volume fader of one group member channel will change the volume of all member channels—while maintaining the level relationships between them. If possible, use a volume fader with a high initial setting

Mute



The Mute status of all member channels is synchronized.



2.3.3 Group Automation



For mix automation, any Group member can act as a “master”. When an automation parameter value is written, the corresponding value of all other Group members is also written, depending on their Automation mode (e. g. Touch or Latch). The data is written individually for each channel. As a result, you can disable the Group later, without affecting the automation of any Group member—and can obviously edit or change channels individually.

2.3.4 Group Handling on the Logic Control

Click-holding the GROUP button allows you to use the SELECT buttons to assign the selected channels to the next free (new) group. You can use the BANK switches during this operation.

While in the Group mode (click and release the GROUP button), you can switch between Groups with  and . The Group number (G1—G9, 10—32) is displayed in the 7-segment ASSIGNMENT display; the first characters of the Group name are displayed in the SMPTE/BAR display.

The LC-Display shows the track names in the top line. The bottom line will indicate the Group properties of the selected Group.  and  switch to further pages of Group properties. The SELECT keys display/edit the assignment of their channel to the currently selected Group.

TRACK+GROUP activates a Track Multi Channel View mode, which allows you to assign each channel to any Group (or turn it “off”) via each channel’s V-Pot. Alternatively, you can enter this mode by pressing TRACK and then  or  until you reach the “Group” page.

2.3.5 Supported Control Surfaces

Logic supports various Control Surfaces besides the Logic Control. More information about Control Surfaces can be found in the folder “Control Surfaces Info” in the section “Service” of your Emagic Software CD. Here’s an overview over the supported devices.

- Emagic Logic Control, Logic Control XT
- Roland SI-24
- Tascam US-224, US-428

2.4 Automation Quick Access

This new feature makes Track Automation extremely fast and simple if you only have one hardware MIDI controller available (e. g. one fader on your MIDI keyboard or even just the Modulation wheel). You can use this single hardware controller to access the currently visible Automation parameter of the selected Track in the Arrange window.

2.4.1 Setting Up Automation Quick Access

Open the Automation Settings dialog: Options > Track Automation > Track Automation Settings...



There is a new section labeled: *Automation Quick Access* which can be enabled or disabled via a checkbox. Once enabled, click the *Learn Message* button below, and move the hardware controller that you’d like to use for Automation Quick Access. The other parameters shown here will immediately identify and indicate the type of control element you are using (even quite exotic formats are supported). Disable the *Learn Message* button, by clicking on it a second time, or close the Automation Quick Access dialog.

Once done, you will have hardware control over any currently visible Automation parameter which is set in the current Arrange track.

Enable/Disable Automation Quick Access

In case you are using the Modulation Wheel for Automation Quick Access (AQA), you might want to switch between using it for AQA and “normal” Modulation Wheel duties—as MIDI controller #1.

This can be done with the global *Toggle Automation Quick Access Key Command*.




2.5 New Options for Digital Mixdown/Bounce

The *Bounce* function allows you to write the signal of an Output object as an audio file, which would otherwise simply be played live. You can initiate the Bounce process(es) by clicking the “*BNC€*” button on the Output object channel that you would like to bounce.


The bounce dialog of Logic 6 has been restructured, and offers a couple of new options...


2.5.1 Bouncing MP3 Format Audio Files

Logic 6 for Mac OS X now allows the bouncing of MP3 (or by its correct name: MPEG-2-Layer-3) format files. This well-known data reduction format for digital audio signals was developed by the Fraunhofer Institute, and allows high compression rates while maintaining quite good audio quality (depending on the compression rate). MP3 is the current standard for audio file exchange via the Internet.

 Due to the fact that encoding an MP3 file equates to a loss of audio quality, you should not use MP3 files during a production if you have access to the same audio data in linear formats such as: AIFF, WAV or SDII.

If you set the *File Format* flip menu in the bounce dialog to *MP3*, you will see all available options for the encoder (which translates the PCM linear format into compressed MP3 files).




-  You can change the default settings for the encoding engine via the Preferences > MP3 Export menu.

For details on the individual MP3 encoding parameters see the *MP3 Export Settings* section, on page 35 of this addendum.

2.5.2 Bounce Mode

The new Bounce dialog option *Bounce Mode* is available in Logic 6 for Mac OS X and Mac OS 9.



In older versions of Logic, bounces were always performed in real-time. The new *Bounce Mode* parameter allows you choose between two options:

- *Realtime*: Creates the bounce file in real-time, as in older versions. Use it whenever you wish to bounce audio and audio instrument tracks *plus* external MIDI sound sources that are routed into the Logic Mixer via (Live) Input objects.
- *Offline*: Accelerates the bounce process—depending on the complexity of your arrangement and available CPU processing power. It also allows the bouncing of complex arrangements that would normally exceed the power of your CPU, if trying to play them in realtime. Offline bouncing, however, is limited to internal sources (audio tracks or audio instrument tracks). The MIDI tracks and Input Objects of Logic's mixer are deactivated during offline bouncing.

- ❗ Please note that the *Offline Bounce Mode* is only available to the Output objects of mixers that belong to native audio driver systems. DSP-based audio hardware (e. g. ProTools) can not make use of offline bouncing due to the nature of its stream-oriented technology.
- ❗ Other software applications, which are fed into your Logic Mixer via ReWire technology are available for offline bounce processes!

During an Offline Bounce, you can see the SPL moving through the song (usually much faster than real-time). A separate “bounce” progress bar is also shown.

Unlike online (realtime) bouncing, audio outputs will be muted during offline bouncing.

3 Arrange Window



3.1 Freeze

Logic 6 introduces a completely new way to save almost 100% of the CPU power used for software instruments and effect plug-ins—namely, the innovative *Freeze* function. You can apply it, individually, to audio tracks or audio instrument tracks.

3.1.1 Concept

Internally, Freeze performs individual offline bounce processes for each “frozen” track. All plug-ins of a track (including software instrument plug-ins, if applicable, along with all related automation data) are rendered into a “freeze file”.

As long as a track is frozen—following the freeze process—this freeze file will play back in place of the original track (and its CPU-hungry plug-ins). The original track and plug-ins are temporarily deactivated, and use no CPU resources.

-  Please note that the Freeze function always bounces *all* of a channel’s signals. If you are using more than one track that addresses the same audio or instrument channel, then all tracks of this channel will be frozen, and cannot be edited independently.
-  Due to technical reasons, the Freeze function is not available for the tracks of DSP-based audio hardware systems (e. g. ProTools), tracks that use plug-ins which are calculated on DSP cards (Powercore, UAD-1, Pulsar etc.), or tracks that use external signal processing devices via the I/O plug-in. You can, however, “freeze” tracks that use Sends to Busses that have inserted DSP-based or I/O plug-ins.

3.1.2 Application

In real-world situations, Freeze allows you to:

- use additional plug-ins or software instruments in further audio or instrument tracks, which would normally not be possible as it would exceed the CPU processing limits of your computer.
- play back songs created on computers with greater CPU power.

Freeze was made for very CPU-intensive processes, which are generally (from higher to lower demand) outlined as follows:

- Software synthesizers with a complex voice architecture
- Plug-ins with a complex structure (e. g. reverbs, filter banks or FFT-based effects)
- Software synthesizers with a simple voice architecture
- Software sampler with active filter
- Software sampler with deactivated filter
- Plug-ins with a simple structure

As long as your computer is able to calculate all active processes in real-time, it is not necessary to freeze a track.

Freeze is recommended whenever your system's power runs short *and* one, or multiple, existing tracks with CPU-intensive instrument and/or effect plug-ins are in a final state, or at least seem to require no further changes for the meantime—i. e. “close to final”.

As long as a track is frozen, its CPU usage is reduced to that of a high resolution audio track, without any effect plug-ins inserted—regardless of the number, or processing demands, of the plug-ins that were used originally.

3.1.3 How to Freeze a Track

It is extremely easy to freeze a track: simply activate the Freeze button—i. e. the button that features a small ice crystal icon. If the Freeze buttons are not visible, activate the View > Track Freeze Switch menu option in the Arrange window.



The Freeze button of the “Audio 1” track

Logic will create freeze files after receiving the next “Play” command. This allows you to activate the Freeze buttons of multiple tracks, and render their freeze files in one go.

During the Freeze process, the SPL will follow the currently rendered position. A floating progress bar window is also displayed.

- ❗ Freeze files are always rendered between the song start and end mark—it is recommended that you check the song end mark in the bar ruler before starting a Freeze process. Please note that the end mark should be adjusted to include feedback-dependent delay repetitions or reverb tails. Empty areas (digital zero) at the end of freeze files will automatically be removed after the Freeze process.
- ❗ You can abort freeze processes by pressing **⌘.7**—in this scenario, the portion of the frozen track(s) that has already been rendered will remain in the freeze file(s), and will be used for playback. Frozen tracks will remain silent beyond this point.
- ❗ The freeze process uses 100% of available CPU power. If, for example, a track uses 40% of the CPU, its freeze file will be created in 2.5 times the realtime speed. If the original tracks uses 100% of the CPU power, the freeze process will happen in (approx.) real-time—even if offline bouncing is used.


Working with Frozen Tracks

Once a track has been frozen, you cannot edit any instrument or plug-in parameters (or related automation data). You can, however, still edit the:

- effect send levels and destinations,
- panorama and surround parameters,
- volume, mute and solo

of frozen tracks—including their automation data.


Whenever you try to edit “forbidden” parameters of frozen tracks, (e. g. plug-in parameters that were rendered into the freeze file), Logic will display an error message.



Error message if you attempt to edit a frozen track

In this situation:

- deactivate the *Freeze* button of the track,
- This will *delete* the freeze file.

 Please note that the track will now use the amount of CPU processing power that it originally required, if you enter “Play” mode.

- perform your edits,
- activate the *Freeze* button again, if required.

It is not possible to cut and re-arrange the freeze files in any way, nor is it possible to mix the freeze files with their originals on a single track—you can use one or the other, not both!

It is also not possible to record audio on frozen tracks. In fact, the *Record* button will be hidden while a track is frozen.

3.1.4 Freeze Files

The temporary freeze files are saved in a folder named “Freeze Files” which is created in the root directory of your song (e. g. the project folder). Usually, you won’t need to access these freeze files directly.

Logic manages these freeze files for you automatically in the background: They are created during the Freeze process, will play back in place of the original tracks (as long as these tracks are frozen), and will be deleted as soon as the *Freeze* button of the corresponding track is deactivated.


In some cases, however, it might be handy to use freeze files directly: e. g. if you want to freeze *all* of your tracks, and use the freeze files for a remix in another studio (on DSP-based systems, for example).

3.2 Arrange Channel Strip



In Logic 6, the Channel Strip of the currently selected Arrange track will appear in the parameter area of the Arrange window, provided that there is sufficient space to display it. If there is not enough vertical room, click the upper left triangles in the Sequence Parameter and/or Instrument Parameter Boxes and/or hide the Toolbox (View > Toolbox). The Arrange Channel Strip allows you to access all of the mixer channel functions (volume, pan, sends, inserts, etc) directly from the Arrange window. Any adjustments you make to a track's Arrange Channel Strip will be reflected in the corresponding Track Mixer and Environment Channel Strip as well.

3.3 Sample-accurate Waveform Display



The Arrange window now displays the actual waveform of an audio file, all the way down to single sample resolution at the highest zoom levels. The new *Waveform vertical zoom* Key Commands make this feature even more useful; for precise Arrange edit operations, and for operations on audio regions with low signal levels.



3.4 New Arrange Icons



Logic 6 introduces a new icon format, offering high resolution, scalable [from 128×128 pixels downwards], and user-definable icons. A few of the new icons are direct replacements for the older Logic icons, but most of the previous icons remain in the program to ensure backwards compatibility. If you vertically zoom a track with new icons sufficiently, you will see the large size icon in addition to the small icon at the top.

3.4.1 User-definable Icons

You can create your own icons for Arrange tracks. These icons must be at the size of 128×128 pixels, and must be saved in the “portable network graphics” format, and must have an alpha channel for transparency. Please note that these files must be saved with the “.png” suffix. The file-name must also start with a three-digit number. If this number is below 325, the corresponding built-in Logic icon will be replaced by your new graphic [you can check the number of existing Logic icons by double-clicking on them in the Instrument Parameter Box].

In OS 9, user icons must be located inside the *Emagic Resources > Icons* subfolder within your *Logic* application folder.

In OS X there are two possible locations for user icons:

The `~/Library/Application Support/Emagic/EmagicResources/Icons` folder can contain icons which are only valid for the particular user [`~` is the user name].

If you save your icons in the root directory—`~/Library/Application Support/Emagic/EmagicResources/Icons`—the icons are valid for all users.

If icons with identical numbers exist in both folders, the icons found in the user folder have priority.

3.4.2 Icon Color

The old, monochromatic icons used to adopt the color of their “parent” Audio Object or MIDI Instrument—which is also still used for newly recorded Regions/Sequences in the Arrange window.

The new high resolution Arrange Icons have their own color and, therefore, can no longer adopt the “parent” object color. To circumvent the overriding color of the new icons, Logic 6 incorporates a small color strip on the right-hand edge of the Track List.

The View > Shadow for Instrument Icons option was removed.

4 Editor Windows

4.1 Chord Recognition in the Matrix Editor


When selecting multiple notes in the Matrix editor, the information section in the upper left corner now displays the chord name of the note combination being played.

5 Audio Standard Support

5.1 MP3 Support (Mac OS X only)

The Mac OS X version of Logic 6 offers full support for the importing and exporting of MP3 files:

5.1.1 MP3 Import

MP3 files may be imported into Logic using the same methods employed when adding AIFF, SDII, or WAV files: namely by -clicking with the pencil tool in the Arrange, using the Audio > Add Audio File command, via the Audio File local menu of the Audio Window, or by dragging MP3 files from the Finder into the Audio Window or Arrange.

When you import MP3 files, Logic converts the MP3 file to an AIFF file, and it is the AIFF file that is used in Logic. Logic does this because many functions, such as waveform display, sample accurate editing, and so on, would tax the CPU if Logic had to constantly decode and re-encode the MP3 files in realtime for each change. By converting the MP3s to AIFF on import, Logic ensures the most efficient use of resources.

5.1.2 MP3 Export

Logic can export MP3 files as well, using technology Apple licensed from the Fraunhofer Institute, the developers of the MP3 format. You can select MP3 as a file format for Bouncing, or by using the “Convert to MP3” command in the Audio File local menu of the Audio Window.

Bouncing MP3 Files


“MP3” is now one of the options in the pull-down *File Format* menu of the *Bounce* dialog. When you select *MP3* as your file format, the bounce options for *Resolution*, *Stereo File Type*, *Surround Bounce* and *Dithering* are replaced by the “MP3 Export Settings” listed below. You can choose to Bounce MP3 files in realtime, or offline.

Convert To MP3

MP3 files can also be created from individual audio files by using the “Convert To MP3” command of the Audio File local menu in the Audio Window. When you create an MP3 file via this command, the encoder uses the Global settings of the MP3 Export Preference dialog, found in the Logic menu.

MP3 Export Settings

Below are the MP3 Export settings found in the Logic > Preferences > MP3 Export menu, along with some usage tips.



Bit Rate (Mono/Stereo)

The bit rates are selectable between *8kbps* and *320kbps*, but default to *80kbps mono*, and *160kbps stereo*. These rates offer acceptable quality and good file compression. If you can afford the extra file size, we recommend *96kbps* for mono, and *192kbps* for stereo streams, as this provides better audio quality. You can, of course, choose even higher rates, but the quality improvement in bit rates above *96/192kbps* is minimal.

Quality

Keep this set to *Highest* whenever possible. Reducing the quality will speed up the conversion process, but at the expense of audio quality.

Use Variable Bit Rate Encoding (VBR)

Variable Bit Rate encoding compresses “simple” passages more heavily than harmonically-rich passages, generally resulting in better quality MP3s. Unfortunately, not all MP3 players can accurately decode VBR-encoded MP3s, which is why this option is turned off by default. If you determine that the listener/s of your MP3 can decode VBR-encoded MP3s, you can switch this option on.

Use Best Encoding

Again, like the *Quality* parameter, you will gain encoding speed at the price of audio quality if this option is unchecked. This should always be left on, unless conversion time is an issue.

Filter Frequencies Below 10Hz

When this option is checked, frequencies below 10Hz (which are usually not reproduced by speakers, and are not audible to human ears, at any rate ...) will be removed, leaving slightly more data bandwidth for the frequencies which we can hear, resulting in an improvement in perceived quality. Only uncheck this if you’re experimenting with subsonic test tones, or exporting MP3s for whales ...

Stereo Mode

You can select joint stereo or normal stereo mode. Depending on the original file, these settings may (or may not) offer any audible difference. Experiment with both settings to determine your preference.

6 Project Manager

File > Save as project...

This global command internally uses the Project Manager's database. Use it to Save a Song with all, or specific data types (audio files, EXS instruments, samples, movie files), into a new folder—i. e. the "Project Folder". This is useful for backing up a production, transferring a song to another studio, or simply to organize your hard disk(s) more efficiently ...

Use of this command will launch the "Consolidate Song Functions" dialog window, where you can enter a "Project Folder Name" and choose from several options (mainly regarding choices to copy, move or simply leave certain file types at their current location(s)).

